



ΕΓΚΑΤΑΣΤΑΣΗ



Windows Movie Maker


ΣΕ WINDOWS 8, 10 & 11




Το έργο υποστηρίζεται από το Ελληνικό Ίδρυμα Έρευνας και Καινοτομίας (ΕΛ.ΙΔ.Ε.Κ.) στο πλαίσιο της 3ης Προκήρυξης της Δράσης «Επιστήμη και Κοινωνία» με τίτλο «Κόμβοι Έρευνας, Καινοτομίας και Διάχυσης» (Αριθμός Έργου: 1708)

ΒΗΜΑ 1

Επισκεφτείτε τη διεύθυνση https://archive.org/details/wlsetup-all_201802 και κατεβάστε το αρχείο εγκατάστασης (Windows executable στο πλαίσιο Download Options στα δεξιά της σελίδας).



 **Microsoft Windows Live Essentials 2012**
by Microsoft Corporation

Publication date: 2012
Topics: Windows Live, Windows Live Suite, Windows Live Essentials, Movie Maker, Microsoft, Microsoft Movie Maker, Photo Gallery, Windows Live Photo Gallery, Live Essentials, Windows Live Mail, Messenger, Microsoft Messenger, Windows Live Messenger, Writer, Windows Live Writer, Microsoft Writer, Essentials 2012, MS Essentials, MS Live Essentials
Language: English

The last version of the Windows Live Essentials software suite. You can no longer download Windows Live Essentials from Microsoft or use the web downloader.

Windows Live Essentials was a free software suite available for Windows, it included a photo gallery, video editor, email client, blogging word processor, OneDrive (an online storage client), and a messaging application. If you run the installer on Windows 7, you can install Family Safety, which adds parental controls features in Windows 7. Since this service is online connected, it probably doesn't work with web reports, as was touted as a headline feature. When it was still being supported and new versions were being released, it was feature-rich software suite.

Windows Live Essentials 2012 has:

- Photo Gallery
- Movie Maker
- Mail (support limited)
- Messenger (no longer functional)
- Writer (newer version available, note: **Newer version no longer developed directly by Microsoft**)
- OneDrive (newer version available)
- Family Safety (Windows 7 only)

You must be running Windows 7 or later to run Windows Live Essentials 2012. Note that some functionality, such as Messenger, no longer function.

521,140 Views
96 Favorites
37 Reviews

DOWNLOAD OPTIONS


TORRENT	1 file
WINDOWS EXECUTABLE	1 file
SHOW ALL	6 Files 6 Original

IN COLLECTIONS

- Community Software
- Community Collections


ΒΗΜΑ 2

Κάντε διπλό κλικ στο αρχείο εγκατάστασης που κατεβάσατε για να εκκινήσει η διαδικασία εγκατάστασης. Στο γκρι πλαίσιο που θα εμφανιστεί, επιλέξτε **Choose the programs you want to install**.



ΒΗΜΑ 3


Στο νέο γκρι πλαίσιο που θα εμφανιστεί με τίτλο **Select programs to install**, βεβαιωθείτε ότι είναι τσεκαρισμένο μόνο το **Photo Gallery and Movie Maker** και πατήστε **Install**.






Στην περίπτωση που επιχειρείτε να εγκαταστήσετε το Movie Maker σε Windows 10, πιθανότατα θα απαιτηθεί η εγκατάσταση του .NET Framework 3.5.

Σε αυτή την περίπτωση, πριν εκκινήσει η εγκατάσταση του Movie Maker, θα σας ζητηθεί να συναινέσετε στην εγκατάσταση του .NET Framework 3.5.



Επιλέξτε την εγκατάσταση του στοιχείου.

Μόλις ολοκληρωθεί η εγκατάσταση του .NET Framework 3.5 και στη συνέχεια του Movie Maker, ενδέχεται να εμφανιστεί μήνυμα που θα σας ενημερώνει ότι η εγκατάσταση απέτυχε.

Παραβλέψτε το συγκεκριμένο μήνυμα. Το Movie Maker έχει εγκατασταθεί στον Υπολογιστή σας και μπορείτε να το επιβεβαιώσετε κάνοντας κλικ στο  : θα πρέπει να βλέπετε στην κορυφή του **Start Menu** το Movie Maker, κάτω από την ένδειξη **Recently installed** ή **Εγκαταστάθηκαν πρόσφατα**.